
Plate Carree



Overview

- A seismic prospect may be surveyed in a pre-defined local projection.
- In the US that might be State Plane coordinates on land or UTM in US Survey Feet in the outer continental shelf of the Gulf of Mexico.
- Local prospects may be gathered regionally or a regional survey may be undertaken.
- In these cases new parameters or a different projection may be required to minimize cartographic distortion over the region.
- Cartographic distortion analysis is the process of computing and plotting distortion contours on a map containing the prospect.
- It is also the process of optimizing projection parameters to minimize distortion in the area of interest (AOI).
- Among conformal projections, e.g. Mercator, Transverse Mercator (TM), Oblique Mercator (OM), Lambert Conformal Conic (LCC) and Stereographic, the two main distortions are (1) point scale factor and (2) convergence of the meridians.
- Two non-conformal projections are treated in this report, the Albers Equal Area and the Ellipsoidal Orthographic (EO).


The defining characteristic of a conformal projection is that the scale factor at a point is uniform in all directions. It is for this reason that angles (not azimuths) in the real world are the same on the map. The point scale factor is the differential ratio of grid distance to geodetic distance.


Azimuths (or directions) in the real world (true azimuths) and azimuths on the map (grid azimuths) will differ in the amount of convergence of the meridians. At a point, convergence is the same in all directions on conformal projections.


On equal-area projections the point scale factor is not the same in all directions. In fact, the factors are reciprocal in orthogonal directions. The product of reciprocal scale factors is unity (1), thus the projection is equal area. Angular distortion is characteristic of an equal-area projection.


The ellipsoidal orthographic is neither conformal nor equal-area, but it has other advantages. It is derived from topographic (ENU) and Earth-Centered Earth-Fixed (ECEF) coordinates.


Plate Carree





































x 16 tereographic Latitude/Longitude Graticule





























Cartographic Characteristics, 1 of 2

- Plate Carrée
 - Not a projection
 - The latitude/longitude, meridian/parallel graticule is the grid
 - No Northings or Eastings, no linear unit (such as meters)
- Mercator
 - Cylindrical axis is the spin axis
 - Meridians and parallels are straight
 - Scale increases north and south
 - No convergence
- Transverse Mercator
 - Cylindrical axis is in the Equatorial plane
 - Meridians and parallels are curved
 - Scale increases east and west
- Oblique Mercator
 - Cylindrical axis is oblique (at an angle to the graticule)
 - Meridians and parallels curved
 - Scale increases away from the central azimuth


Cartographic Characteristics, 2 of 2


- Lambert Conformal Conic
 - Conical axis is the spin axis
 - Meridians straight and parallels curved
 - Scale increases north and south
- Stereographic
 - Azimuthal plane
 - Meridians and parallels curved
 - Scale increases circularly
- Albers Equal Area
 - Conical axis is the spin axis
 - Orthogonal scales at a point are reciprocal
 - Thus, the equal-area property
- Ellipsoidal Orthographic
 - Azimuthal plane
 - The view from space, not conformal, not equal area
 - Scale in the circular direction always unity (1)

Afterword on Transverse Mercator

TM (Gauss-Kruger) algorithms approximate elliptical integrals with infinite series expansions that are necessarily truncated. The earliest TM implementations (Redfearn, Thomas, Snyder, US Department of the Army, which "invented" the UTM grid system) truncated severely to suit the computational equipment of the day. Collectively, these are called "narrow-zone" algorithms because the round-trip error begins to mount annoyingly about 4 to 5 degrees from the CM. New, wide-zone implementations are stable 40 degrees from the CM, some as many as 90 degrees.

But since many TM implementations are "narrow zone", another potential distortion is narrow-zone round-trip error when working outside of the width of a UTM zone. The following two plots show narrow-zone and wide-zone round-trip error.





Concluding Comments

- This brief presentation is only a sampler. It cannot be exhaustive.
- Several useful projections and many characteristics are not covered
- Specific projects require specific projections and specific parameters for those projections
- Consult with a geodesist if in doubt about what's best for your project
- LCC and Albers are conic projections with the same parameters, but different results
- Stereographic and Orthographic are planar azimuthal projections with the same parameters, but different results
- More information on narrow-zone and wide-zone TM can be found here: <u>http://www.hydrometronics.com/downloads/EPSG%20Wide-Zone%20TM%20r2.pdf</u>
- More information on Ellipsoidal Orthographic can be found here: <u>http://www.hydrometronics.com/downloads/Ellipsoidal%20Orthograp</u> <u>hic%20Projection.pdf</u>